



Running SLAM

Hongrui Zheng (hongruiz@seas.upenn.edu)

Installing slam_toolbox

```
sudo apt install ros-foxy-slam-toolbox
```

Before running slam_toolbox

Make sure the odometry on your car is tuned!

Launching slam_toolbox

- Launch teleop in one window
- Launch slam_toolbox
 - `ros2 launch slam_toolbox online_async_launch.py
params_file:=/home/nvidia/f1tenth_ws/src/f1tenth_system/f1te
nth_stack/config/f1tenth_online_async.yaml`

Visualization

- Launch rviz2
- Add /map by topic
- Add /graph_visualization by topic
- On top left corner of rviz, panels – add new panel – add SlamToolBoxPlugin panel
- Once you're done mapping, save the map using the plugin. You can give it a name in the text box next to Save Map. Map will be saved in whichever directory you ran slam_toolbox.



Running Particle Filter

Hongrui Zheng (hongruiz@seas.upenn.edu)

Installing range_libc

- Clone the repo:
 - `cd`
 - `git clone https://github.com/f1tenth/range_libc.git`
- Install with:
 - `cd range_libc/pywrapper`
 - `sudo WITH_CUDA=ON python setup.py install`

Installing particle filter

- Clone the package
 - `cd /home/nvidia/f1tenth_ws/src`
 - `git clone https://github.com/f1tenth/particle_filter.git`
- Install dependencies
 - `rosdep install -r --from-paths src --ignore-src --rosdistro foxy -y`
- Compile workspace again
 - `cd /home/nvidia/f1tenth_ws && colcon build`
 - `source install/setup.bash`

Running Particle Filter

1. Launch teleop
2. Launch particle filter with:

```
ros2 launch particle_filter localize_launch.py
```

Visualizing

1. Run rviz2
2. Use add by topic, add map. In the settings for map, change durability policy under topic to transient local
3. To show the current localization, add /pf/viz/inferred_pose
4. Optionally, you can add /pf/viz/particles to see the particles


Checking the update frequency

Check the publishing frequency on
`/pf/viz/inferred_pose`. It should be at least 30 Hz.

Changing the map used

1. Put the map files (image+.yaml) in
particle_filter/maps
2. Change particle_filter/config/localize.yaml to
reflect the map you want to use

Set Initial position



Use the 2D Pose Estimate to set the initial position
For the particle filter